Rletopnm User Manual

RLETOPNM

Updated: 13 April 2000
Table Of Contents

NAME

rletopnm - convert a Utah Raster Tools RLE image file to a PNM image file.

SYNOPSIS

rletopnm [**--alphaout=**{*alpha-filename*,**-**}] [**--headerdump**|**-h**] [**--verbose**|**-v**] [*rlefile*|**-**]

All options may be abbreviated to their minimum unique abbreviation and options and arguments may be in any order.

DESCRIPTION

This program is part of Netpbm.

rletopnm converts Utah Raster Toolkit RLE image files to PNM image files. **rletopnm** handles four types of RLE files: Grayscale (8 bit data, no color map), Pseudocolor (8 bit data with a color map), Truecolor (24 bit data with color map), and Directcolor (24 bit data, no color map). **rletopnm** generates a PPM file for all these cases except for the Grayscale file, for which **rletopnm** generates a PGM file.

rlefile is the RLE input file. If it is absent or **-**, the input comes from Standard Input.

OPTIONS

--alphaout=*alpha-filename***rletopnm** creates a PGM (portable graymap) file containing the alpha channel values in the input image. If the input image doesn't contain an alpha channel, the *alpha-filename* file contains all zero (transparent) alpha values. If you don't specify **--alphaout**, **rletopnm** does not generate an alpha file, and if the input image has an alpha channel, **rletopnm** simply discards it.

If you specify **-** as the filename, **rletopnm** writes the alpha output to Standard Output and discards the image.

See **pamcomp** for one way to use the alpha output file.

--verbose This option causes **rletopnm** to operate in verbose mode. It prints messages about what it's doing, including the contents of the RLE image header, to Standard Error.

--headerdump This option causes **rletopnm** to operate in header dump mode. It prints the contents of the RLE image header to Standard Error, but does not produce any other output.

EXAMPLES

While running in verbose mode, convert lenna.rle to PPM format and store the resulting image as lenna.ppm:

```
rletopnm --verbose lenna.rle >lenna.ppm
```

Dump the header information of the RLE file called file.rle:

```
rletopnm --headerdump file.rle
```

Convert RLE file dart.rle to PPM format as dart.ppm. Store the alpha channel of dart.rle as dartalpha.pgm (if dart.rle doesn't have an alpha channel, store a fully transparent alpha mask as dartalpha.pgm):

```
rletopnm --alphaout=dartalpha.pgm dart.rle >dart.ppm
```

SEE ALSO

pnmtorle, **pnmconvol**, **pnm**, **ppm**, **pgm**,

AUTHOR

Wes Barris
Army High Performance Computing Research Center (AHPCRC)
Minnesota Supercomputer Center, Inc.

Modifications by Eric Haines to support raw and plain formats.

Modifications by Bryan Henderson to create alpha files and use mnemonic options.

Table Of Contents

SYNOPSIS
DESCRIPTION
OPTIONS
EXAMPLES
SEE ALSO
AUTHOR